
CARDIAC CATHETERIZATION PRACTICE TEST (SAMPLE)

STUDY GUIDE



SAMPLE STUDY GUIDE WITH LIMITED QUESTIONS

VISIT US ONLINE FOR THE FULL VERSION STUDY GUIDE

https://cardiaccatheterization.examzify.com

Copyright © 2026 by Examzify - A Kaluba Technologies Inc. product.

ALL RIGHTS RESERVED.

No part of this book may be reproduced or transferred in any form or by any means, graphic, electronic, or mechanical, including photocopying, recording, web distribution, taping, or by any information storage retrieval system, without the written permission of the author.

Notice: Examzify makes every reasonable effort to obtain accurate, complete, and timely information about this product from reliable sources.

SAMPLE

Table of Contents

Copyright 1

Table of Contents 2

Introduction 3

How to Use This Guide 4

Questions 5

Answers 8

Explanations 10

Next Steps 16

SAMPLE

Introduction

Preparing for a certification exam can feel overwhelming, but with the right tools, it becomes an opportunity to build confidence, sharpen your skills, and move one step closer to your goals. At Examzify, we believe that effective exam preparation isn't just about memorization, it's about understanding the material, identifying knowledge gaps, and building the test-taking strategies that lead to success.

This guide was designed to help you do exactly that.

Whether you're preparing for a licensing exam, professional certification, or entry-level qualification, this book offers structured practice to reinforce key concepts. You'll find a wide range of multiple-choice questions, each followed by clear explanations to help you understand not just the right answer, but why it's correct.

The content in this guide is based on real-world exam objectives and aligned with the types of questions and topics commonly found on official tests. It's ideal for learners who want to:

- Practice answering questions under realistic conditions,
- Improve accuracy and speed,
- Review explanations to strengthen weak areas, and
- Approach the exam with greater confidence.

We recommend using this book not as a stand-alone study tool, but alongside other resources like flashcards, textbooks, or hands-on training. For best results, we recommend working through each question, reflecting on the explanation provided, and revisiting the topics that challenge you most.

Remember: successful test preparation isn't about getting every question right the first time, it's about learning from your mistakes and improving over time. Stay focused, trust the process, and know that every page you turn brings you closer to success.

Let's begin.

SAMPLE

How to Use This Guide

This guide is designed to help you study more effectively and approach your exam with confidence. Whether you're reviewing for the first time or doing a final refresh, here's how to get the most out of your Examzify study guide:

1. Start with a Diagnostic Review

Skim through the questions to get a sense of what you know and what you need to focus on. Your goal is to identify knowledge gaps early.

2. Study in Short, Focused Sessions

Break your study time into manageable blocks (e.g. 30 – 45 minutes). Review a handful of questions, reflect on the explanations.

3. Learn from the Explanations

After answering a question, always read the explanation, even if you got it right. It reinforces key points, corrects misunderstandings, and teaches subtle distinctions between similar answers.

4. Track Your Progress

Use bookmarks or notes (if reading digitally) to mark difficult questions. Revisit these regularly and track improvements over time.

5. Simulate the Real Exam

Once you're comfortable, try taking a full set of questions without pausing. Set a timer and simulate test-day conditions to build confidence and time management skills.

6. Repeat and Review

Don't just study once, repetition builds retention. Re-attempt questions after a few days and revisit explanations to reinforce learning. Pair this guide with other Examzify tools like flashcards, and digital practice tests to strengthen your preparation across formats.

There's no single right way to study, but consistent, thoughtful effort always wins. Use this guide flexibly, adapt the tips above to fit your pace and learning style. You've got this!

SAMPLE

Questions

SAMPLE

1. What is balloon atrial septostomy and in what condition is it used?

A. A procedure to create or enlarge an atrial septal communication to improve systemic oxygenation in certain congenital heart defects (e.g., d-TGA) or in neonatal palliation.

B. A technique to close atrial septal defects.

C. A method to widen the ventricular septum.

D. A device to occlude patent ductus arteriosus.

2. How does instantaneous wave-free ratio (iFR) differ from invasive FFR?

A. iFR uses rest without pharmacologic vasodilation; FFR uses hyperemia.

B. FFR uses rest without pharmacologic vasodilation; iFR uses pharmacologic hyperemia.

C. iFR uses hyperemia; FFR uses rest.

D. They are identical in measurement approach.

3. During procedures that use a transeptal approach, which chamber is accessed directly?

A. Right atrium

B. Left atrium

C. Right ventricle

D. Pulmonary artery

4. Which factors increase the risk of stent thrombosis and how can it be mitigated?

A. Not using antiplatelet therapy

B. Adequate stent expansion; prolonged DAPT; low-risk lesion

C. Inadequate stent expansion, early discontinuation of dual antiplatelet therapy, high-risk lesion; mitigation includes optimal deployment, appropriate DAPT duration, and antithrombotic management.

D. No risk factors for stent thrombosis

5. What pressure is obtained when the balloon is deflated?

A. Right atrial pressure

B. Left atrial pressure

C. Pulmonary artery pressure

D. Systemic arterial pressure

SAMPLE

6. Which term describes removing plaque with a catheter-mounted cutting device, rotating blade, or laser?

A. Atherectomy

B. Stenting

C. Angioplasty

D. Thrombolysis

7. Which signs suggest acute pericardial tamponade after catheterization?

A. Hypotension, tachycardia, muffled heart sounds, jugular venous distension

B. Hypertension, bradycardia

C. Normal heart sounds, no JVD

D. Fever and leukocytosis

8. How do preload and afterload relate to invasive hemodynamic measurements?

A. Preload (filling pressures like PCWP) affects LV stroke volume; afterload (SVR) influences arterial pressure and cardiac workload

B. Preload increases afterload

C. Afterload decreases preload

D. They are unrelated

9. In PCI, thrombus aspiration is particularly beneficial in which scenario?

A. In all cases regardless of lesion characteristics.

B. When there is no thrombus.

C. For non-thrombotic lesions only.

D. In thrombotic or high-risk lesions to reduce distal embolization and no-reflow.

10. Which statement describes the contrast used in LV angiography?

A. A contrast agent containing iodine is injected to make the structure visible on X-ray

B. A gadolinium-based agent is used for MRI

C. Contrast is not used in LV angiography

D. The contrast is absorbed by the tissues to measure chemical composition

SAMPLE

Answers

SAMPLE

1. D
2. A
3. B
4. C
5. C
6. A
7. A
8. D
9. D
10. A

SAMPLE

Explanations

SAMPLE

1. What is balloon atrial septostomy and in what condition is it used?

A. A procedure to create or enlarge an atrial septal communication to improve systemic oxygenation in certain congenital heart defects (e.g., d-TGA) or in neonatal palliation.

B. A technique to close atrial septal defects.

C. A method to widen the ventricular septum.

D. A device to occlude patent ductus arteriosus.

Balloon atrial septostomy creates or enlarges an opening between the atria to promote mixing of oxygenated and deoxygenated blood, which is crucial when the great arteries are transposed and there isn't good systemic oxygenation. In newborns with dextro-transposition of the great arteries, the only way to improve systemic oxygen delivery before definitive repair is through atrial level mixing, achieved by tearing the atrial septum with a balloon catheter to enlarge the interatrial communication. This technique, sometimes performed as part of neonatal palliation, helps raise systemic oxygen saturation until surgical correction can be done. It is not used to close an atrial septal defect, nor to widen the ventricular septum, nor to occlude a patent ductus arteriosus.

2. How does instantaneous wave-free ratio (iFR) differ from invasive FFR?

A. iFR uses rest without pharmacologic vasodilation; FFR uses hyperemia.

B. FFR uses rest without pharmacologic vasodilation; iFR uses pharmacologic hyperemia.

C. iFR uses hyperemia; FFR uses rest.

D. They are identical in measurement approach.

Instantaneous wave-free ratio (iFR) is measured at rest, during a specific wave-free period in diastole when microvascular resistance is naturally low and stable, so no pharmacologic vasodilator is used. Invasive FFR, on the other hand, requires inducing maximal hyperemia with a vasodilator (such as adenosine) to minimize and standardize microvascular resistance, which allows the pressure drop across a stenosis to reflect its true impact under those hyperemic conditions. In other words, iFR compares distal and proximal pressures at rest without vasodilators, while FFR compares them during maximal hyperemia. This distinction is why iFR is described as resting and hyperemia-free, whereas FFR relies on hyperemia to unmask the stenosis's effect.

3. During procedures that use a transeptal approach, which chamber is accessed directly?

A. Right atrium

B. Left atrium

C. Right ventricle

D. Pulmonary artery

A transeptal approach directly targets the left atrium. It involves puncturing the interatrial septum, usually at the fossa ovalis, from the right atrium to create a direct path into the left atrium for catheter access. This is what makes the left atrium the chamber being accessed. The right atrium is where the procedure typically starts, but the goal of this technique is to reach the left atrium in one step. The right ventricle and pulmonary artery are not accessed directly by this method.

SAMPLE

4. Which factors increase the risk of stent thrombosis and how can it be mitigated?

A. Not using antiplatelet therapy

B. Adequate stent expansion; prolonged DAPT; low-risk lesion

C. Inadequate stent expansion, early discontinuation of dual antiplatelet therapy, high-risk lesion; mitigation includes optimal deployment, appropriate DAPT duration, and antithrombotic management.

D. No risk factors for stent thrombosis

The core idea here is understanding what factors raise the risk of a stent clot forming and how to reduce that danger through careful technique and therapy. Inadequate stent expansion leaves areas where the stent does not properly contact the vessel wall. This creates turbulent flow and exposes struts to blood, promoting platelet activation and thrombus formation. The remedy is meticulous deployment with proper sizing and adequate expansion, often confirmed with intravascular imaging (like IVUS or OCT) to ensure the stent is fully apposed and well expanded. Discontinuation of dual antiplatelet therapy too early removes the antiplatelet protection while the stent surface is still healing, allowing platelets to aggregate on exposed stent struts. The mitigation involves continuing dual antiplatelet therapy for the recommended duration based on the stent type and patient bleeding risk, then tailoring duration to balance ischemic protection with bleeding risk. High-risk lesion characteristics—such as calcified or long lesions, bifurcations, small vessels, ostial locations, or lesions with heavy thrombus—also raise thrombosis risk. Address this with thorough lesion preparation (e.g., plaque modification techniques for calcified lesions), ensuring optimal stent deployment, and selecting an appropriate antiplatelet strategy and duration. Overall, preventing stent thrombosis hinges on optimal deployment, adherence to the recommended antiplatelet therapy duration, and careful antithrombotic management tailored to the patient and lesion.

5. What pressure is obtained when the balloon is deflated?

A. Right atrial pressure

B. Left atrial pressure

C. Pulmonary artery pressure

D. Systemic arterial pressure

The balloon-tipped pulmonary artery catheter can read different pressures depending on whether the balloon is inflated or deflated. When the balloon is inflated, the catheter wedges in a small branch of the pulmonary artery, which isolates a column of blood and yields the left atrial pressure estimate (pulmonary capillary wedge pressure). When the balloon is deflated, the catheter's tip remains in the pulmonary artery and the pressure readout reflects the pressures within the pulmonary arterial system itself. Therefore, with the balloon deflated, the pressure you obtain is the pulmonary artery pressure.

SAMPLE

6. Which term describes removing plaque with a catheter-mounted cutting device, rotating blade, or laser?

A. Atherectomy

B. Stenting

C. Angioplasty

D. Thrombolysis

The term describes removing plaque with a catheter-mounted cutting device, rotating blade, or laser: atherectomy. The goal of atherectomy is to physically debulk or modify the atherosclerotic plaque to enlarge the vessel lumen. Different forms include directional atherectomy, which uses a cutter to shave plaque; rotational atherectomy, which employs a high-speed burr to grind away calcium-bridged plaque; and laser atherectomy, which vaporizes tissue with laser energy. This approach differs from balloon angioplasty, which simply sweeps or compresses plaque to widen the artery without removing it; stenting, which places a scaffold to keep the vessel open after intervention; and thrombolysis, which dissolves clots rather than plaque.

7. Which signs suggest acute pericardial tamponade after catheterization?

A. Hypotension, tachycardia, muffled heart sounds, jugular venous distension

B. Hypertension, bradycardia

C. Normal heart sounds, no JVD

D. Fever and leukocytosis

Acute pericardial tamponade after catheterization happens when blood or fluid quickly accumulates in the pericardial space, compressing the heart and impairing filling. The falling stroke volume leads to low blood pressure, and the body responds with a fast heart rate, so tachycardia is common. The fluid around the heart muffles the heart sounds, making them harder to hear, and the elevated pressure in the chest reduces venous return, causing jugular venous distension as blood backs up in the neck veins. Pulsus paradoxus may also be present, reflecting exaggerated fall in systolic blood pressure during inspiration. This combination—hypotension, tachycardia, muffled heart sounds, and jugular venous distension—best fits tamponade after a procedure. Hypertension with bradycardia wouldn't match tamponade physiology. Normal heart sounds with no JVD suggests no pericardial effusion. Fever and leukocytosis point more toward infection or inflammation rather than acute tamponade.

SAMPLE

8. How do preload and afterload relate to invasive hemodynamic measurements?

A. Preload (filling pressures like PCWP) affects LV stroke volume; afterload (SVR) influences arterial pressure and cardiac workload

B. Preload increases afterload

C. Afterload decreases preload

D. They are unrelated

Preload and afterload are the two main determinants that shape what we measure with invasive hemodynamics. Preload describes the filling condition of the heart—how much blood returns to the heart and how stretched the ventricles are at the end of diastole. When we line up invasive measurements, this shows up as filling pressures: central venous pressure for the right side and pulmonary capillary wedge pressure for the left side. Because of the Frank-Starling relationship, higher preload tends to increase the stroke volume (up to the heart's limit), provided contractility is adequate. Afterload is the pressure the heart has to overcome to eject blood. In practice, this is reflected by arterial pressure, especially mean arterial pressure, and by systemic vascular resistance and arterial impedance. A higher afterload makes ejection more difficult, which can reduce stroke volume and raise myocardial oxygen demand. Invasive measurements of arterial pressure and derived resistance give a window into afterload. So, preload and afterload are not unrelated to invasive hemodynamics. Preload tells us how much the ventricle is filled and ready to pump; afterload tells us how hard the ventricle must work to eject that blood. Together, they help explain changes in stroke volume and cardiac output and guide interpretation of catheter-derived pressures and flows.

9. In PCI, thrombus aspiration is particularly beneficial in which scenario?

A. In all cases regardless of lesion characteristics.

B. When there is no thrombus.

C. For non-thrombotic lesions only.

D. In thrombotic or high-risk lesions to reduce distal embolization and no-reflow.

Thrombus aspiration during PCI aims to lower distal embolization and the no-reflow phenomenon by removing thrombus from the culprit vessel. This approach is most advantageous when there is a substantial thrombus burden or high risk thrombotic lesions because taking the clot out reduces debris that could be dislodged during balloon or stent passage, helping to preserve microvascular perfusion. If there is no thrombus or the lesion is non-thrombotic, the benefit is minimal and the procedure can add time or risk without improving outcomes. Therefore, it is particularly beneficial in thrombotic or high risk lesions to reduce distal embolization and no-reflow.

SAMPLE

10. Which statement describes the contrast used in LV angiography?

A. A contrast agent containing iodine is injected to make the structure visible on X-ray

B. A gadolinium-based agent is used for MRI

C. Contrast is not used in LV angiography

D. The contrast is absorbed by the tissues to measure chemical composition

LV angiography relies on an iodinated, radiopaque contrast agent injected into the left ventricle to outline the chamber on X-ray imaging. The iodine's high atomic number makes it show up brightly on fluoroscopy, allowing clear visualization of the left ventricle's size, shape, and wall motion during cine imaging. This is why the statement about an iodine-containing contrast making the structure visible on X-ray is the best choice. Gadolinium-based agents are used for MRI, not X-ray angiography, so they don't apply here. The idea that contrast is absorbed by tissues to measure chemical composition isn't how radiographic angiography works—images depend on differences in X-ray attenuation, not tissue chemical analysis.

SAMPLE

Next Steps

Congratulations on reaching the final section of this guide. You've taken a meaningful step toward passing your certification exam and advancing your career.

As you continue preparing, remember that consistent practice, review, and self-reflection are key to success. Make time to revisit difficult topics, simulate exam conditions, and track your progress along the way.

If you need help, have suggestions, or want to share feedback, we'd love to hear from you. Reach out to our team at hello@examzify.com.

Or visit your dedicated course page for more study tools and resources:

https://cardiaccatheterization.examzify.com

We wish you the very best on your exam journey. You've got this!

SAMPLE