REGISTERED CARDIOVASCULAR INVASIVE SPECIALIST (RCIS) PRACTICE TEST (SAMPLE)

STUDY GUIDE



SAMPLE STUDY GUIDE WITH LIMITED QUESTIONS

VISIT US ONLINE FOR THE FULL VERSION STUDY GUIDE

https://rcis.examzify.com

Copyright © 2026 by Examzify - A Kaluba Technologies Inc. product.

ALL RIGHTS RESERVED.

No part of this book may be reproduced or transferred in any form or by any means, graphic, electronic, or mechanical, including photocopying, recording, web distribution, taping, or by any information storage retrieval system, without the written permission of the author.

Notice: Examzify makes every reasonable effort to obtain accurate, complete, and timely information about this product from reliable sources.

SAMPLE

Table of Contents

Copyright 1

Table of Contents 2

Introduction 3

How to Use This Guide 4

Questions 5

Answers 8

Explanations 10

Next Steps 15

SAMPLE

Introduction

Preparing for a certification exam can feel overwhelming, but with the right tools, it becomes an opportunity to build confidence, sharpen your skills, and move one step closer to your goals. At Examzify, we believe that effective exam preparation isn't just about memorization, it's about understanding the material, identifying knowledge gaps, and building the test-taking strategies that lead to success.

This guide was designed to help you do exactly that.

Whether you're preparing for a licensing exam, professional certification, or entry-level qualification, this book offers structured practice to reinforce key concepts. You'll find a wide range of multiple-choice questions, each followed by clear explanations to help you understand not just the right answer, but why it's correct.

The content in this guide is based on real-world exam objectives and aligned with the types of questions and topics commonly found on official tests. It's ideal for learners who want to:

- Practice answering questions under realistic conditions,
- Improve accuracy and speed,
- Review explanations to strengthen weak areas, and
- Approach the exam with greater confidence.

We recommend using this book not as a stand-alone study tool, but alongside other resources like flashcards, textbooks, or hands-on training. For best results, we recommend working through each question, reflecting on the explanation provided, and revisiting the topics that challenge you most.

Remember: successful test preparation isn't about getting every question right the first time, it's about learning from your mistakes and improving over time. Stay focused, trust the process, and know that every page you turn brings you closer to success.

Let's begin.

SAMPLE

How to Use This Guide

This guide is designed to help you study more effectively and approach your exam with confidence. Whether you're reviewing for the first time or doing a final refresh, here's how to get the most out of your Examzify study guide:

1. Start with a Diagnostic Review

Skim through the questions to get a sense of what you know and what you need to focus on. Your goal is to identify knowledge gaps early.

2. Study in Short, Focused Sessions

Break your study time into manageable blocks (e.g. 30 – 45 minutes). Review a handful of questions, reflect on the explanations.

3. Learn from the Explanations

After answering a question, always read the explanation, even if you got it right. It reinforces key points, corrects misunderstandings, and teaches subtle distinctions between similar answers.

4. Track Your Progress

Use bookmarks or notes (if reading digitally) to mark difficult questions. Revisit these regularly and track improvements over time.

5. Simulate the Real Exam

Once you're comfortable, try taking a full set of questions without pausing. Set a timer and simulate test-day conditions to build confidence and time management skills.

6. Repeat and Review

Don't just study once, repetition builds retention. Re-attempt questions after a few days and revisit explanations to reinforce learning. Pair this guide with other Examzify tools like flashcards, and digital practice tests to strengthen your preparation across formats.

There's no single right way to study, but consistent, thoughtful effort always wins. Use this guide flexibly, adapt the tips above to fit your pace and learning style. You've got this!

SAMPLE

Questions

SAMPLE

1. What is the formula for calculating cardiac output?

A. CO = HR x SV

B. CO = SV + HR

C. CO = SVR x BP

D. CO = HR - SV

2. Which of the following is NOT classified as an ACE inhibitor?

A. Enalapril

B. Lasix

C. Lisinopril

D. Ramipril

3. Which medication should not be administered to a patient taking NPH insulin?

A. Insulin Glargine

B. Protamine

C. Metformin

D. Glucose

4. If the heart rate slows, what typically happens to stroke volume?

A. Increases

B. Decreases

C. Remains the same

D. Varies unpredictably

5. What is the best short-acting medication/anxiolytic to sedate a patient?

A. Atenolol

B. Versed/Midazolam

C. Fentanyl

D. Diazepam

6. Cardiac output is primarily measured using which parameter?

A. Pulmonary systolic pressure

B. Heart rate

C. SVC pressure

D. Stroke volume

SAMPLE

7. Which component is critical in determining cardiac preload?

A. Afterload

B. Blood volume

C. Heart rate

D. Vascular resistance

8. How far from the distal tip is the blue proximal port of the Swan catheter typically located?

A. 45 cm

B. 30 cm

C. 15 cm

D. 60 cm

9. Which factor does NOT contribute to an increased risk of stroke?

A. A Fib

B. Hypertension

C. Regular physical activity

D. A Flutter

10. Lidocaine converts from 2GM in 500cc to what concentration?

A. 6 mg in 1 cc

B. 4 mg in 1 cc

C. 2 mg in 1 cc

D. 10 mg in 1 cc

SAMPLE

Answers

SAMPLE

1. A
2. B
3. B
4. A
5. B
6. D
7. B
8. B
9. C
10. B

SAMPLE

Explanations

SAMPLE

1. What is the formula for calculating cardiac output?

A. CO = HR x SV

B. CO = SV + HR

C. CO = SVR x BP

D. CO = HR - SV

The formula for calculating cardiac output is CO = HR x SV, where CO represents cardiac output, HR is heart rate, and SV stands for stroke volume. This formula indicates that cardiac output is the product of how many times the heart beats per minute (heart rate) and the amount of blood pumped out of the heart with each beat (stroke volume). This relationship is essential in understanding how the heart functions to meet the body's demands for oxygen and nutrients. When either heart rate or stroke volume increases, cardiac output will also increase, which is crucial during exercise or in situations where the body requires more blood flow. This formula is fundamental in cardiovascular physiology and is widely used in clinical settings to assess heart function and overall cardiovascular health.

2. Which of the following is NOT classified as an ACE inhibitor?

A. Enalapril

B. Lasix

C. Lisinopril

D. Ramipril

Lasix is a diuretic, specifically a loop diuretic, that is commonly used to remove excess fluid from the body by increasing urine production. It works by inhibiting sodium and chloride reabsorption in the kidneys, leading to increased excretion of these electrolytes along with water. In contrast, ACE inhibitors, like Enalapril, Lisinopril, and Ramipril, function by blocking the action of the angiotensin-converting enzyme (ACE), which plays a crucial role in the body's renin-angiotensin-aldosterone system (RAAS). This action helps to lower blood pressure and reduce the workload on the heart. Understanding these medication classes is vital for cardiovascular care, as it informs treatment decisions for conditions such as hypertension and heart failure. Thus, in this context, Lasix is not classified as an ACE inhibitor, making it the correct answer for this question.

3. Which medication should not be administered to a patient taking NPH insulin?

A. Insulin Glargine

B. Protamine

C. Metformin

D. Glucose

Administering Protamine to a patient taking NPH insulin is inadvisable due to its potential effects on insulin pharmacology. Protamine is a protein that is commonly used to reverse the effects of heparin, an anticoagulant. It can also have an interaction with insulin formulations. NPH (Neutral Protamine Hagedorn) insulin is an intermediate-acting insulin that already contains protamine as part of its formulation to prolong the insulin's action. When protamine is administered in addition to NPH, it may further prolong the duration of action of the insulin, leading to an increased risk of hypoglycemia. Therefore, it's crucial to avoid administering protamine to ensure safe blood glucose management in patients receiving NPH insulin. While the other options, such as Insulin Glargine, Metformin, and Glucose, can be safely used alongside NPH insulin under proper medical supervision, Protamine introduces a risk that can complicate the patient's treatment plan.

SAMPLE

4. If the heart rate slows, what typically happens to stroke volume?

A. Increases

B. Decreases

C. Remains the same

D. Varies unpredictably

When the heart rate slows, the stroke volume typically increases. This relationship can be understood through the concept of cardiac output, which is the product of heart rate and stroke volume. In a situation where the heart rate decreases, the ventricles have more time to fill with blood during diastole. This increased filling time often leads to a greater volume of blood being expelled with each contraction, thus enhancing stroke volume. Additionally, a slower heart rate may allow the heart to function more efficiently, as it can generate a stronger contraction due to the increased preload, which is the volume of blood in the ventricles at the end of diastole. This phenomenon aligns with the Frank-Starling mechanism of the heart, where increased venous return and ventricular filling results in greater stretch of the myocardial fibers, ultimately increasing the force of contraction and the volume of blood pumped out with each heartbeat. While other variables, such as contractility and afterload, can also impact stroke volume, the general physiological response to a decrease in heart rate is an increase in stroke volume, making the answer accurate within the context of normal cardiac physiology.

5. What is the best short-acting medication/anxiolytic to sedate a patient?

A. Atenolol

B. Versed/Midazolam

C. Fentanyl

D. Diazepam

Midazolam, commonly known by its brand name Versed, is considered the best short-acting medication/anxiolytic for sedating a patient due to its rapid onset and relatively short duration of action. As a benzodiazepine, Midazolam works by enhancing the effect of the neurotransmitter gamma-aminobutyric acid (GABA) at the benzodiazepine receptor site, leading to increased sedation, anxiolysis, and amnesia. This makes it particularly effective in procedural sedation and management of anxiety before surgical interventions or other procedures. In comparison, other medications listed have different primary uses or are not specifically designed for short-term sedation. Atenolol, for instance, is primarily a beta-blocker used for hypertension and cardiac conditions, lacking sedative effects. Fentanyl is a potent opioid analgesic and, while it can cause sedation as a side effect, it is primarily used for pain management or anesthesia rather than as a first-line anxiolytic. Diazepam, another benzodiazepine, has a longer half-life and may not be suitable for scenarios requiring quick-acting sedative properties. Thus, in settings where short-acting sedation is essential, Midazolam is preferred for its efficacy and rapid action

SAMPLE

6. Cardiac output is primarily measured using which parameter?

A. Pulmonary systolic pressure

B. Heart rate

C. SVC pressure

D. Stroke volume

Cardiac output is fundamentally defined as the product of heart rate and stroke volume. Stroke volume specifically refers to the amount of blood ejected by the heart's left ventricle with each contraction. By measuring stroke volume, which reflects the efficient functioning of the heart itself including aspects like preload, afterload, and contractility, clinicians can determine the volume of blood the heart pumps in a given time frame, usually expressed in liters per minute. While heart rate does play a significant role in cardiac output, it is the stroke volume that is directly related to the volume of blood being circulated with each beat. Therefore, understanding and measuring stroke volume is vital in determining cardiac output accurately, making it the primary parameter for this measurement. Other options, such as pulmonary systolic pressure and SVC pressure, do not directly reflect cardiac output, as they pertain to different physiological or anatomical aspects of the cardiovascular system. Thus, recognizing stroke volume as a crucial measure in calculating cardiac output reinforces its importance in cardiovascular assessments.

7. Which component is critical in determining cardiac preload?

A. Afterload

B. Blood volume

C. Heart rate

D. Vascular resistance

Blood volume is critical in determining cardiac preload because it directly influences the amount of blood returning to the heart during diastole, which is the heart's filling phase. Preload refers to the initial stretching of the cardiac muscle fibers due to the volume of blood in the ventricles just before contraction. An increase in blood volume leads to increased venous return, thereby augmenting preload. Understanding preload is key to grasping how the heart fills and how effectively it can pump blood throughout the body. Other factors, while they influence cardiac function, do not directly affect the volume of blood in the ventricles as significantly as blood volume does. Afterload relates to the resistance the heart must overcome to eject blood, heart rate affects the frequency of contractions but not the initial filling, and vascular resistance impacts blood flow but does not determine how much blood returns to the heart for filling. Thus, blood volume is fundamentally linked to preload and is essential for optimal cardiac function.

SAMPLE

8. How far from the distal tip is the blue proximal port of the Swan catheter typically located?

A. 45 cm

B. 30 cm

C. 15 cm

D. 60 cm

The blue proximal port of the Swan-Ganz catheter is typically located approximately 30 cm from the distal tip of the catheter. Understanding this distance is crucial for healthcare professionals as it helps in accurately positioning the catheter for hemodynamic monitoring and ensuring correct readings of pressures in the heart and pulmonary artery. The access and functionality of the Swan catheter are defined by its design, where the distal tip is intended for pulmonary artery pressure measurement. Meanwhile, the proximal port is used for the infusion of fluids and for obtaining central venous pressure readings. The specific distance, such as 30 cm, is designed to provide effective access to these functions and ensure that the ports are positioned appropriately within the anatomical structures they are meant to evaluate or interact with. This knowledge is essential for proper catheter placement, as incorrect positioning can lead to misinterpretation of hemodynamic data or complications related to catheter use.

9. Which factor does NOT contribute to an increased risk of stroke?

A. A Fib

B. Hypertension

C. Regular physical activity

D. A Flutter

Regular physical activity is associated with a reduced risk of stroke rather than an increased risk. Engaging in consistent physical activity has numerous cardiovascular benefits, including improved blood circulation, maintained healthy blood pressure levels, and reduced body weight—all of which contribute to better overall heart health. Conversely, conditions like Atrial Fibrillation (A Fib) and Atrial Flutter (A Flutter) both increase the risk of stroke by promoting the formation of blood clots in the heart. Hypertension, or high blood pressure, is another significant risk factor for stroke, as it can lead to damage of the blood vessels over time, increasing susceptibility to strokes. Thus, while A Fib, hypertension, and A Flutter each heighten the likelihood of stroke occurrence, regular physical activity serves as a protective factor.

10. Lidocaine converts from 2GM in 500cc to what concentration?

A. 6 mg in 1 cc

B. 4 mg in 1 cc

C. 2 mg in 1 cc

D. 10 mg in 1 cc

To determine the concentration of lidocaine when 2 grams (2GM) are dissolved in 500 cc, you need to convert grams to milligrams and then calculate the concentration. First, convert grams to milligrams: 2 grams is equal to 2000 milligrams since 1 gram is 1000 milligrams. Next, to find the concentration in mg per cc, divide the total milligrams by the total volume in cc: 2000 mg / 500 cc = 4 mg/cc. Thus, the concentration of lidocaine in this case is 4 mg in 1 cc. This calculation shows the correct understanding of converting units and calculating concentration in solution. The other options present different concentrations which do not match the calculated value.

SAMPLE

Next Steps

Congratulations on reaching the final section of this guide. You've taken a meaningful step toward passing your certification exam and advancing your career.

As you continue preparing, remember that consistent practice, review, and self-reflection are key to success. Make time to revisit difficult topics, simulate exam conditions, and track your progress along the way.

If you need help, have suggestions, or want to share feedback, we'd love to hear from you. Reach out to our team at hello@examzify.com.

Or visit your dedicated course page for more study tools and resources:

https://rcis.examzify.com

We wish you the very best on your exam journey. You've got this!

SAMPLE